

*D R A F T*

# Document for a Standard Message-Passing Interface

Message Passing Interface Forum

February 14, 2015

This work was supported in part by NSF and ARPA under NSF contract CDA-9115428 and Esprit under project HPC Standards (21111).

This is the result of a LaTeX run of a draft of a single chapter of the MPIF Final Report document.

## Chapter 8

# MPI Environmental Management

This chapter discusses routines for getting and, where appropriate, setting various parameters that relate to the MPI implementation and the execution environment (such as error handling). The procedures for entering and leaving the MPI execution environment are also described here.

### 8.1 Implementation Information

#### 8.1.1 Version Inquiries

In order to cope with changes to the MPI Standard, there are both compile-time and run-time ways to determine which version of the standard is in use in the environment one is using.

The “version” will be represented by two separate integers, for the version and subversion: In C,

```
#define MPI_VERSION    3
#define MPI_SUBVERSION 0
```

in Fortran,

```
INTEGER :: MPI_VERSION, MPI_SUBVERSION
PARAMETER (MPI_VERSION    = 3)
PARAMETER (MPI_SUBVERSION = 0)
```

For runtime determination,

`MPI_GET_VERSION( version, subversion )`

OUT	version	version number (integer)
OUT	subversion	subversion number (integer)

```
int MPI_Get_version(int *version, int *subversion)
```

```
MPI_Get_version(version, subversion, ierror)
  INTEGER, INTENT(OUT) :: version, subversion
  INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```

1 MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)
2     INTEGER VERSION, SUBVERSION, IERROR

```

MPI\_GET\_VERSION can be called before MPI\_INIT and after MPI\_FINALIZE. Valid (MPI\_VERSION, MPI\_SUBVERSION) pairs in this and previous versions of the MPI standard are (3,0), (2,2), (2,1), (2,0), and (1,2). This function is callable from threads without restriction, see Section 12.4.

```

9 MPI_GET_LIBRARY_VERSION( version, resultlen )

```

OUT	version	version string (string)
OUT	resultlen	Length (in printable characters) of the result returned in version (integer)

```

15 int MPI_Get_library_version(char *version, int *resultlen)

```

```

16 MPI_Get_library_version(version, resultlen, ierror)
17     CHARACTER(LEN=MPI_MAX_LIBRARY_VERSION_STRING), INTENT(OUT) :: version
18     INTEGER, INTENT(OUT) :: resultlen
19     INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

21 MPI_GET_LIBRARY_VERSION(VERSION, RESULTLEN, IERROR)
22     CHARACTER*(*) VERSION
23     INTEGER RESULTLEN, IERROR

```

This routine returns a string representing the version of the MPI library. The version argument is a character string for maximum flexibility.

*Advice to implementors.* An implementation of MPI should return a different string for every change to its source code or build that could be visible to the user. (*End of advice to implementors.*)

The argument `version` must represent storage that is MPI\_MAX\_LIBRARY\_VERSION\_STRING characters long. MPI\_GET\_LIBRARY\_VERSION may write up to this many characters into `version`.

The number of characters actually written is returned in the output argument, `resultlen`. In C, a null character is additionally stored at `version[resultlen]`. The value of `resultlen` cannot be larger than MPI\_MAX\_LIBRARY\_VERSION\_STRING - 1. In Fortran, `version` is padded on the right with blank characters. The value of `resultlen` cannot be larger than MPI\_MAX\_LIBRARY\_VERSION\_STRING.

MPI\_GET\_LIBRARY\_VERSION can be called before MPI\_INIT and after MPI\_FINALIZE.

### 8.1.2 Environmental Inquiries

A set of attributes that describe the execution environment are attached to the communicator MPI\_COMM\_WORLD when MPI is initialized. The values of these attributes can be inquired by using the function MPI\_COMM\_GET\_ATTR described in Section 6.7 and in Section 17.2.7. It is erroneous to delete these attributes, free their keys, or change their values.

The list of predefined attribute keys include

**MPI\_TAG\_UB** Upper bound for tag value.

**MPI\_HOST** Host process rank, if such exists, MPI\_PROC\_NULL, otherwise.

**MPI\_IO** rank of a node that has regular I/O facilities (possibly myrank). Nodes in the same communicator may return different values for this parameter.

**MPI\_WTIME\_IS\_GLOBAL** Boolean variable that indicates whether clocks are synchronized.

Vendors may add implementation-specific parameters (such as node number, real memory size, virtual memory size, etc.)

These predefined attributes do not change value between MPI initialization (MPI\_INIT) and MPI completion (MPI\_FINALIZE), and cannot be updated or deleted by users.

*Advice to users.* Note that in the C binding, the value returned by these attributes is a *pointer* to an `int` containing the requested value. (*End of advice to users.*)

The required parameter values are discussed in more detail below:

### Tag Values

Tag values range from 0 to the value returned for MPI\_TAG\_UB, inclusive. These values are guaranteed to be unchanging during the execution of an MPI program. In addition, the tag upper bound value must be *at least* 32767. An MPI implementation is free to make the value of MPI\_TAG\_UB larger than this; for example, the value  $2^{30} - 1$  is also a valid value for MPI\_TAG\_UB.

The attribute MPI\_TAG\_UB has the same value on all processes of MPI\_COMM\_WORLD.

### Host Rank

The value returned for MPI\_HOST gets the rank of the *HOST* process in the group associated with communicator MPI\_COMM\_WORLD, if there is such. MPI\_PROC\_NULL is returned if there is no host. MPI does not specify what it means for a process to be a *HOST*, nor does it require that a *HOST* exists.

The attribute MPI\_HOST has the same value on all processes of MPI\_COMM\_WORLD.

### IO Rank

The value returned for MPI\_IO is the rank of a processor that can provide language-standard I/O facilities. For Fortran, this means that all of the Fortran I/O operations are supported (e.g., OPEN, REWIND, WRITE). For C, this means that all of the ISO C I/O operations are supported (e.g., fopen, fprintf, lseek).

If every process can provide language-standard I/O, then the value MPI\_ANY\_SOURCE will be returned. Otherwise, if the calling process can provide language-standard I/O, then its rank will be returned. Otherwise, if some process can provide language-standard I/O then the rank of one such process will be returned. The same value need not be returned by all processes. If no process can provide language-standard I/O, then the value MPI\_PROC\_NULL will be returned.

*Advice to users.* Note that input is not collective, and this attribute does *not* indicate which process can or does provide input. (*End of advice to users.*)

## 1 Clock Synchronization

2 The value returned for `MPI_WTIME_IS_GLOBAL` is 1 if clocks at all processes in  
 3 `MPI_COMM_WORLD` are synchronized, 0 otherwise. A collection of clocks is considered  
 4 synchronized if explicit effort has been taken to synchronize them. The expectation is that  
 5 the variation in time, as measured by calls to `MPI_WTIME`, will be less than one half the  
 6 round-trip time for an MPI message of length zero. If time is measured at a process just  
 7 before a send and at another process just after a matching receive, the second time should  
 8 be always higher than the first one.

9 The attribute `MPI_WTIME_IS_GLOBAL` need not be present when the clocks are not  
 10 synchronized (however, the attribute key `MPI_WTIME_IS_GLOBAL` is always valid). This  
 11 attribute may be associated with communicators other than `MPI_COMM_WORLD`.

12 The attribute `MPI_WTIME_IS_GLOBAL` has the same value on all processes of  
 13 `MPI_COMM_WORLD`.

## 15 Inquire Processor Name

18 `MPI_GET_PROCESSOR_NAME( name, resultlen )`

20	OUT	name	A unique specifier for the actual (as opposed to virtual) node.
22	OUT	resultlen	Length (in printable characters) of the result returned in name

25 `int MPI_Get_processor_name(char *name, int *resultlen)`

26 `MPI_Get_processor_name(name, resultlen, ierror)`  
 27 `CHARACTER(LEN=MPI_MAX_PROCESSOR_NAME), INTENT(OUT) :: name`  
 28 `INTEGER, INTENT(OUT) :: resultlen`  
 29 `INTEGER, OPTIONAL, INTENT(OUT) :: ierror`

31 `MPI_GET_PROCESSOR_NAME( NAME, RESULTLEN, IERROR)`  
 32 `CHARACTER*(*) NAME`  
 33 `INTEGER RESULTLEN, IERROR`

35 This routine returns the name of the processor on which it was called at the moment  
 36 of the call. The name is a character string for maximum flexibility. From this value it  
 37 must be possible to identify a specific piece of hardware; possible values include “processor  
 38 9 in rack 4 of mpp.cs.org” and “231” (where 231 is the actual processor number in the  
 39 running homogeneous system). The argument `name` must represent storage that is at least  
 40 `MPI_MAX_PROCESSOR_NAME` characters long. `MPI_GET_PROCESSOR_NAME` may write  
 41 up to this many characters into `name`.

42 The number of characters actually written is returned in the output argument, `resultlen`.  
 43 In C, a null character is additionally stored at `name[resultlen]`. The value of `resultlen` cannot  
 44 be larger than `MPI_MAX_PROCESSOR_NAME-1`. In Fortran, `name` is padded on the right with  
 45 blank characters. The value of `resultlen` cannot be larger than `MPI_MAX_PROCESSOR_NAME`.

46  
 47 *Rationale.* This function allows MPI implementations that do process migration to  
 48 return the current processor. Note that nothing in MPI *requires* or defines process

migration; this definition of `MPI_GET_PROCESSOR_NAME` simply allows such an implementation. (*End of rationale.*)

*Advice to users.* The user must provide at least `MPI_MAX_PROCESSOR_NAME` space to write the processor name — processor names can be this long. The user should examine the output argument, `resultlen`, to determine the actual length of the name. (*End of advice to users.*)

## 8.2 Memory Allocation

In some systems, message-passing and remote-memory-access (RMA) operations run faster when accessing specially allocated memory (e.g., memory that is shared by the other processes in the communicating group on an SMP). MPI provides a mechanism for allocating and freeing such special memory. The use of such memory for message-passing or RMA is not mandatory, and this memory can be used without restrictions as any other dynamically allocated memory. However, implementations may restrict the use of some RMA functionality as defined in Section 11.5.3.

`MPI_ALLOC_MEM(size, info, baseptr)`

IN	size	size of memory segment in bytes (non-negative integer)
IN	info	info argument (handle)
OUT	baseptr	pointer to beginning of memory segment allocated

```
int MPI_Alloc_mem(MPI_Aint size, MPI_Info info, void *baseptr)
```

```
MPI_Alloc_mem(size, info, baseptr, ierror)
  USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
  INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
  TYPE(MPI_Info), INTENT(IN) :: info
  TYPE(C_PTR), INTENT(OUT) :: baseptr
  INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)
  INTEGER INFO, IERROR
  INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
```

If the Fortran compiler provides `TYPE(C_PTR)`, then the following generic interface must be provided in the `mpi` module and should be provided in `mpif.h` through overloading, i.e., with the same routine name as the routine with `INTEGER(KIND=MPI_ADDRESS_KIND) BASEPTR`, but with a different specific procedure name:

```
INTERFACE MPI_ALLOC_MEM
  SUBROUTINE MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)
    IMPORT :: MPI_ADDRESS_KIND
    INTEGER INFO, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
```

```

1      END SUBROUTINE
2      SUBROUTINE MPI_ALLOC_MEM_CPTR(SIZE, INFO, BASEPTR, IERROR)
3          USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
4          IMPORT :: MPI_ADDRESS_KIND
5          INTEGER :: INFO, IERROR
6          INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE
7          TYPE(C_PTR) :: BASEPTR
8      END SUBROUTINE
9  END INTERFACE

```

The base procedure name of this overloaded function is `MPI_ALLOC_MEM_CPTR`. The implied specific procedure names are described in Section 17.1.5.

The `info` argument can be used to provide directives that control the desired location of the allocated memory. Such a directive does not affect the semantics of the call. Valid `info` values are implementation-dependent; a null directive value of `info = MPI_INFO_NULL` is always valid.

The function `MPI_ALLOC_MEM` may return an error code of class `MPI_ERR_NO_MEM` to indicate it failed because memory is exhausted.

```

20  MPI_FREE_MEM(base)

```

22	IN	base	initial address of memory segment allocated by MPI_ALLOC_MEM (choice)
----	----	------	--

```

25  int MPI_Free_mem(void *base)

```

```

26  MPI_Free_mem(base, ierror)
27      TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: base
28      INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

30  MPI_FREE_MEM(BASE, IERROR)

```

```

31      <type> BASE(*)
32      INTEGER IERROR

```

The function `MPI_FREE_MEM` may return an error code of class `MPI_ERR_BASE` to indicate an invalid base argument.

*Rationale.* The C bindings of `MPI_ALLOC_MEM` and `MPI_FREE_MEM` are similar to the bindings for the `malloc` and `free` C library calls: a call to `MPI_Alloc_mem(..., &base)` should be paired with a call to `MPI_Free_mem(base)` (one less level of indirection). Both arguments are declared to be of same type `void*` so as to facilitate type casting. The Fortran binding is consistent with the C bindings: the Fortran `MPI_ALLOC_MEM` call returns in `baseptr` the `TYPE(C_PTR)` pointer or the (integer valued) address of the allocated memory. The `base` argument of `MPI_FREE_MEM` is a choice argument, which passes (a reference to) the variable stored at that location. (*End of rationale.*)

*Advice to implementors.* If `MPI_ALLOC_MEM` allocates special memory, then a design similar to the design of C `malloc` and `free` functions has to be used, in order



to find out the size of a memory segment, when the segment is freed. If no special memory is used, MPI\_ALLOC\_MEM simply invokes `malloc`, and MPI\_FREE\_MEM invokes `free`.

A call to MPI\_ALLOC\_MEM can be used in shared memory systems to allocate memory in a shared memory segment. (*End of advice to implementors.*)

**Example 8.1** Example of use of MPI\_ALLOC\_MEM, in Fortran with TYPE(C\_PTR) pointers. We assume 4-byte REALs.

```
USE mpi_f08      ! or USE mpi      (not guaranteed with INCLUDE 'mpif.h')
USE, INTRINSIC :: ISO_C_BINDING
TYPE(C_PTR) :: p
REAL, DIMENSION(:,:), POINTER :: a      ! no memory is allocated
INTEGER, DIMENSION(2) :: shape
INTEGER(KIND=MPI_ADDRESS_KIND) :: size
shape = (/100,100/)
size = 4 * shape(1) * shape(2)          ! assuming 4 bytes per REAL
CALL MPI_Alloc_mem(size,MPI_INFO_NULL,p,ierr) ! memory is allocated and
CALL C_F_POINTER(p, a, shape) ! intrinsic ! now accessible via a(i,j)
...                                     ! in ISO_C_BINDING
a(3,5) = 2.71;
...
CALL MPI_Free_mem(a, ierr)              ! memory is freed
```

**Example 8.2** Example of use of MPI\_ALLOC\_MEM, in Fortran with non-standard *Cray-pointers*. We assume 4-byte REALs, and assume that these pointers are address-sized.

```
REAL A
POINTER (P, A(100,100)) ! no memory is allocated
INTEGER(KIND=MPI_ADDRESS_KIND) SIZE
SIZE = 4*100*100
CALL MPI_ALLOC_MEM(SIZE, MPI_INFO_NULL, P, IERR)
! memory is allocated
...
A(3,5) = 2.71;
...
CALL MPI_FREE_MEM(A, IERR) ! memory is freed
```

This code is not Fortran 77 or Fortran 90 code. Some compilers may not support this code or need a special option, e.g., the GNU gFortran compiler needs `-fcray-pointer`.

*Advice to implementors.* Some compilers map Cray-pointers to address-sized integers, some to TYPE(C\_PTR) pointers (e.g., Cray Fortran, version 7.3.3). From the user's viewpoint, this mapping is irrelevant because Examples 8.2 should work correctly with an MPI-3.0 (or later) library if Cray-pointers are available. (*End of advice to implementors.*)

**Example 8.3** Same example, in C.

```

1  float  (* f)[100][100];
2  /* no memory is allocated */
3  MPI_Alloc_mem(sizeof(float)*100*100, MPI_INFO_NULL, &f);
4  /* memory allocated */
5  ...
6  (*f)[5][3] = 2.71;
7  ...
8  MPI_Free_mem(f);

```

### 8.3 Error Handling

An MPI implementation cannot or may choose not to handle some errors that occur during MPI calls. These can include errors that generate exceptions or traps, such as floating point errors or access violations. The set of errors that are handled by MPI is implementation-dependent. Each such error generates an *MPI exception*.

The above text takes precedence over any text on error handling within this document. Specifically, text that states that errors *will* be handled should be read as *may* be handled.

A user can associate error handlers to three types of objects: communicators, windows, and files. The specified error handling routine will be used for any MPI exception that occurs during a call to MPI for the respective object. MPI calls that are not related to any objects are considered to be attached to the communicator MPI\_COMM\_WORLD. The attachment of error handlers to objects is purely local: different processes may attach different error handlers to corresponding objects.

Several predefined error handlers are available in MPI:

**MPI\_ERRORS\_ARE\_FATAL** The handler, when called, causes the program to abort on all executing processes. This has the same effect as if MPI\_ABORT was called by the process that invoked the handler.

**MPI\_ERRORS\_RETURN** The handler has no effect other than returning the error code to the user.

Implementations may provide additional predefined error handlers and programmers can code their own error handlers.

The error handler MPI\_ERRORS\_ARE\_FATAL is associated by default with MPI\_COMM\_WORLD after initialization. Thus, if the user chooses not to control error handling, every error that MPI handles is treated as fatal. Since (almost) all MPI calls return an error code, a user may choose to handle errors in its main code, by testing the return code of MPI calls and executing a suitable recovery code when the call was not successful. In this case, the error handler MPI\_ERRORS\_RETURN will be used. Usually it is more convenient and more efficient not to test for errors after each MPI call, and have such error handled by a non-trivial MPI error handler.

After an error is detected, the state of MPI is undefined. That is, using a user-defined error handler, or MPI\_ERRORS\_RETURN, does *not* necessarily allow the user to continue to use MPI after an error is detected. The purpose of these error handlers is to allow a user to issue user-defined error messages and to take actions unrelated to MPI (such as flushing I/O buffers) before a program exits. An MPI implementation is free to allow MPI to continue after an error but is not required to do so.

*Advice to implementors.* A high-quality implementation will, to the greatest possible extent, circumscribe the impact of an error, so that normal processing can continue after an error handler was invoked. The implementation documentation will provide information on the possible effect of each class of errors. (*End of advice to implementors.*)

An MPI error handler is an opaque object, which is accessed by a handle. MPI calls are provided to create new error handlers, to associate error handlers with objects, and to test which error handler is associated with an object. C has distinct typedefs for user defined error handling callback functions that accept communicator, file, and window arguments. In Fortran there are three user routines.

An error handler object is created by a call to `MPI_XXX_CREATE_ERRHANDLER`, where XXX is, respectively, COMM, WIN, or FILE.

An error handler is attached to a communicator, window, or file by a call to `MPI_XXX_SET_ERRHANDLER`. The error handler must be either a predefined error handler, or an error handler that was created by a call to `MPI_XXX_CREATE_ERRHANDLER`, with matching XXX. The predefined error handlers `MPI_ERRORS_RETURN` and `MPI_ERRORS_ARE_FATAL` can be attached to communicators, windows, and files.

The error handler currently associated with a communicator, window, or file can be retrieved by a call to `MPI_XXX_GET_ERRHANDLER`.

The MPI function `MPI_ERRHANDLER_FREE` can be used to free an error handler that was created by a call to `MPI_XXX_CREATE_ERRHANDLER`.

`MPI_{COMM,WIN,FILE}_GET_ERRHANDLER` behave as if a new error handler object is created. That is, once the error handler is no longer needed, `MPI_ERRHANDLER_FREE` should be called with the error handler returned from `MPI_{COMM,WIN,FILE}_GET_ERRHANDLER` to mark the error handler for deallocation. This provides behavior similar to that of `MPI_COMM_GROUP` and `MPI_GROUP_FREE`.

*Advice to implementors.* High-quality implementations should raise an error when an error handler that was created by a call to `MPI_XXX_CREATE_ERRHANDLER` is attached to an object of the wrong type with a call to `MPI_YYY_SET_ERRHANDLER`. To do so, it is necessary to maintain, with each error handler, information on the typedef of the associated user function. (*End of advice to implementors.*)

The syntax for these calls is given below.

### 8.3.1 Error Handlers for Communicators

`MPI_COMM_CREATE_ERRHANDLER(comm_errhandler_fn, errhandler)`

IN	<code>comm_errhandler_fn</code>	user defined error handling procedure (function)
OUT	<code>errhandler</code>	MPI error handler (handle)

```
int MPI_Comm_create_errhandler(MPI_Comm_errhandler_function
                               *comm_errhandler_fn, MPI_Errhandler *errhandler)
```

```
MPI_Comm_create_errhandler(comm_errhandler_fn, errhandler, ierror)
```

```

1      PROCEDURE(MPI_Comm_errhandler_function) :: comm_errhandler_fn
2      TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
3      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
4
5      MPI_COMM_CREATE_ERRHANDLER(COMM_ERRHANDLER_FN, ERRHANDLER, IERROR)
6      EXTERNAL COMM_ERRHANDLER_FN
7      INTEGER ERRHANDLER, IERROR

```

Creates an error handler that can be attached to communicators.

The user routine should be, in C, a function of type `MPI_Comm_errhandler_function`, which is defined as

```

11     typedef void MPI_Comm_errhandler_function(MPI_Comm *, int *, ...);

```

The first argument is the communicator in use. The second is the error code to be returned by the MPI routine that raised the error. If the routine would have returned `MPI_ERR_IN_STATUS`, it is the error code returned in the status for the request that caused the error handler to be invoked. The remaining arguments are “`varargs`” arguments whose number and meaning is implementation-dependent. An implementation should clearly document these arguments. Addresses are used so that the handler may be written in Fortran. With the Fortran `mpi_f08` module, the user routine `comm_errhandler_fn` should be of the form:

```

20     ABSTRACT INTERFACE
21     SUBROUTINE MPI_Comm_errhandler_function(comm, error_code)
22         TYPE(MPI_Comm) :: comm
23         INTEGER :: error_code
24     END SUBROUTINE

```

With the Fortran `mpi` module and `mpif.h`, the user routine `COMM_ERRHANDLER_FN` should be of the form:

```

27     SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE)
28         INTEGER COMM, ERROR_CODE
29     END SUBROUTINE

```

*Rationale.* The variable argument list is provided because it provides an ISO-standard hook for providing additional information to the error handler; without this hook, ISO C prohibits additional arguments. (*End of rationale.*)

*Advice to users.* A newly created communicator inherits the error handler that is associated with the “parent” communicator. In particular, the user can specify a “global” error handler for all communicators by associating this handler with the communicator `MPI_COMM_WORLD` immediately after initialization. (*End of advice to users.*)

```

41     MPI_COMM_SET_ERRHANDLER(comm, errhandler)
42
43     INOUT    comm                communicator (handle)
44     IN       errhandler          new error handler for communicator (handle)
45
46     int MPI_Comm_set_errhandler(MPI_Comm comm, MPI_Errhandler errhandler)
47
48     MPI_Comm_set_errhandler(comm, errhandler, ierror)

```

```

    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_COMM_SET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
    INTEGER COMM, ERRHANDLER, IERROR

```

Attaches a new error handler to a communicator. The error handler must be either a predefined error handler, or an error handler created by a call to MPI\_COMM\_CREATE\_ERRHANDLER.

```

MPI_COMM_GET_ERRHANDLER(comm, errhandler)
    IN      comm      communicator (handle)
    OUT     errhandler error handler currently associated with communicator
                     (handle)

```

```

int MPI_Comm_get_errhandler(MPI_Comm comm, MPI_Errhandler *errhandler)
MPI_Comm_get_errhandler(comm, errhandler, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
    INTEGER COMM, ERRHANDLER, IERROR

```

Retrieves the error handler currently associated with a communicator.

For example, a library function may register at its entry point the current error handler for a communicator, set its own private error handler for this communicator, and restore before exiting the previous error handler.

### 8.3.2 Error Handlers for Windows

```

MPI_WIN_CREATE_ERRHANDLER(win_errhandler_fn, errhandler)
    IN      win_errhandler_fn      user defined error handling procedure (function)
    OUT     errhandler      MPI error handler (handle)
int MPI_Win_create_errhandler(MPI_Win_errhandler_function
                             *win_errhandler_fn, MPI_Errhandler *errhandler)
MPI_Win_create_errhandler(win_errhandler_fn, errhandler, ierror)
    PROCEDURE(MPI_Win_errhandler_function) :: win_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_WIN_CREATE_ERRHANDLER(WIN_ERRHANDLER_FN, ERRHANDLER, IERROR)
    EXTERNAL WIN_ERRHANDLER_FN

```

1       INTEGER ERRHANDLER, IERROR

2       Creates an error handler that can be attached to a window object. The user routine  
3       should be, in C, a function of type `MPI_Win_errhandler_function` which is defined as  
4       **typedef void MPI\_Win\_errhandler\_function(MPI\_Win \*, int \*, ...);**  
5

6       The first argument is the window in use, the second is the error code to be returned.  
7       With the Fortran `mpi_f08` module, the user routine `win_errhandler_fn` should be of the form:

8       **ABSTRACT INTERFACE**

9       **SUBROUTINE MPI\_Win\_errhandler\_function(win, error\_code)**

10        **TYPE(MPI\_Win) :: win**

11        **INTEGER :: error\_code**

12       With the Fortran `mpi` module and `mpif.h`, the user routine `WIN_ERRHANDLER_FN` should  
13       be of the form:

14       **SUBROUTINE WIN\_ERRHANDLER\_FUNCTION(WIN, ERROR\_CODE)**

15        **INTEGER WIN, ERROR\_CODE**

16  
17  
18       **MPI\_WIN\_SET\_ERRHANDLER(win, errhandler)**

19        **INOUT**    win                               window (handle)

20        **IN**       errhandler                       new error handler for window (handle)

21  
22  
23       **int MPI\_Win\_set\_errhandler(MPI\_Win win, MPI\_Errhandler errhandler)**

24       **MPI\_Win\_set\_errhandler(win, errhandler, ierror)**

25        **TYPE(MPI\_Win), INTENT(IN) :: win**

26        **TYPE(MPI\_Errhandler), INTENT(IN) :: errhandler**

27        **INTEGER, OPTIONAL, INTENT(OUT) :: ierror**

28  
29       **MPI\_WIN\_SET\_ERRHANDLER(WIN, ERRHANDLER, IERROR)**

30        **INTEGER WIN, ERRHANDLER, IERROR**

31  
32       Attaches a new error handler to a window. The error handler must be either a pre-  
33       defined error handler, or an error handler created by a call to  
34       **MPI\_WIN\_CREATE\_ERRHANDLER.**  
35

36  
37       **MPI\_WIN\_GET\_ERRHANDLER(win, errhandler)**

38        **IN**       win                               window (handle)

39        **OUT**       errhandler                      error handler currently associated with window (han-  
40   dle)

41  
42       **int MPI\_Win\_get\_errhandler(MPI\_Win win, MPI\_Errhandler \*errhandler)**

43       **MPI\_Win\_get\_errhandler(win, errhandler, ierror)**

44        **TYPE(MPI\_Win), INTENT(IN) :: win**

45        **TYPE(MPI\_Errhandler), INTENT(OUT) :: errhandler**

46        **INTEGER, OPTIONAL, INTENT(OUT) :: ierror**  
47  
48

```

MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
    INTEGER WIN, ERRHANDLER, IERROR

```

Retrieves the error handler currently associated with a window.

### 8.3.3 Error Handlers for Files

```

MPI_FILE_CREATE_ERRHANDLER(file_errhandler_fn, errhandler)
    IN      file_errhandler_fn      user defined error handling procedure (function)
    OUT     errhandler              MPI error handler (handle)

```

```

int MPI_File_create_errhandler(MPI_File_errhandler_function
    *file_errhandler_fn, MPI_Errhandler *errhandler)

```

```

MPI_File_create_errhandler(file_errhandler_fn, errhandler, ierror)
    PROCEDURE(MPI_File_errhandler_function) :: file_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

MPI_FILE_CREATE_ERRHANDLER(FILE_ERRHANDLER_FN, ERRHANDLER, IERROR)
    EXTERNAL FILE_ERRHANDLER_FN
    INTEGER ERRHANDLER, IERROR

```

Creates an error handler that can be attached to a file object. The user routine should be, in C, a function of type `MPI_File_errhandler_function`, which is defined as

```

typedef void MPI_File_errhandler_function(MPI_File *, int *, ...);

```

The first argument is the file in use, the second is the error code to be returned. With the Fortran `mpi_f08` module, the user routine `file_errhandler_fn` should be of the form:

```

ABSTRACT INTERFACE
    SUBROUTINE MPI_File_errhandler_function(file, error_code)
        TYPE(MPI_File) :: file
        INTEGER :: error_code

```

With the Fortran `mpi` module and `mpif.h`, the user routine `FILE_ERRHANDLER_FN` should be of the form:

```

SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
    INTEGER FILE, ERROR_CODE

```

```

MPI_FILE_SET_ERRHANDLER(file, errhandler)
    INOUT  file              file (handle)
    IN     errhandler        new error handler for file (handle)

```

```

int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)

```

```

MPI_File_set_errhandler(file, errhandler, ierror)
    TYPE(MPI_File), INTENT(IN) :: file

```

```

1      TYPE(MPI_Errhandler), INTENT(IN) ::  errhandler
2      INTEGER, OPTIONAL, INTENT(OUT) ::  ierror
3
4  MPI_FILE_SET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
5      INTEGER FILE, ERRHANDLER, IERROR

```

Attaches a new error handler to a file. The error handler must be either a predefined error handler, or an error handler created by a call to `MPI_FILE_CREATE_ERRHANDLER`.

```

9
10 MPI_FILE_GET_ERRHANDLER(file, errhandler)
11     IN          file                      file (handle)
12     OUT         errhandler                error handler currently associated with file (handle)

```

```

14
15 int MPI_File_get_errhandler(MPI_File file, MPI_Errhandler *errhandler)

```

```

16 MPI_File_get_errhandler(file, errhandler, ierror)
17     TYPE(MPI_File), INTENT(IN) ::  file
18     TYPE(MPI_Errhandler), INTENT(OUT) ::  errhandler
19     INTEGER, OPTIONAL, INTENT(OUT) ::  ierror

```

```

20 MPI_FILE_GET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
21     INTEGER FILE, ERRHANDLER, IERROR

```

Retrieves the error handler currently associated with a file.

### 8.3.4 Freeing Errorhandlers and Retrieving Error Strings

```

28 MPI_ERRHANDLER_FREE( errhandler )
29
30     INOUT      errhandler                MPI error handler (handle)

```

```

32 int MPI_Errhandler_free(MPI_Errhandler *errhandler)

```

```

33 MPI_Errhandler_free(errhandler, ierror)
34     TYPE(MPI_Errhandler), INTENT(INOUT) ::  errhandler
35     INTEGER, OPTIONAL, INTENT(OUT) ::  ierror

```

```

37 MPI_ERRHANDLER_FREE(ERRHANDLER, IERROR)
38     INTEGER ERRHANDLER, IERROR

```

Marks the error handler associated with `errhandler` for deallocation and sets `errhandler` to `MPI_ERRHANDLER_NULL`. The error handler will be deallocated after all the objects associated with it (communicator, window, or file) have been deallocated.



MPI_ERROR_STRING( errorcode, string, resultlen )			1
IN	errorcode	Error code returned by an MPI routine	2
OUT	string	Text that corresponds to the errorcode	3
OUT	resultlen	Length (in printable characters) of the result returned in string	4
			5
			6

```
int MPI_Error_string(int errorcode, char *string, int *resultlen)
```

```

MPI_Error_string(errorcode, string, resultlen, ierror)
  INTEGER, INTENT(IN) :: errorcode
  CHARACTER(LEN=MPI_MAX_ERROR_STRING), INTENT(OUT) :: string
  INTEGER, INTENT(OUT) :: resultlen
  INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

MPI_ERROR_STRING(ERRORCODE, STRING, RESULTLEN, IERROR)
  INTEGER ERRORCODE, RESULTLEN, IERROR
  CHARACTER*(*) STRING

```

Returns the error string associated with an error code or class. The argument `string` must represent storage that is at least `MPI_MAX_ERROR_STRING` characters long.

The number of characters actually written is returned in the output argument, `resultlen`.

*Rationale.* The form of this function was chosen to make the Fortran and C bindings similar. A version that returns a pointer to a string has two difficulties. First, the return string must be statically allocated and different for each error message (allowing the pointers returned by successive calls to `MPI_ERROR_STRING` to point to the correct message). Second, in Fortran, a function declared as returning `CHARACTER*(*)` can not be referenced in, for example, a `PRINT` statement. (*End of rationale.*)

## 8.4 Error Codes and Classes

The error codes returned by MPI are left entirely to the implementation (with the exception of `MPI_SUCCESS`). This is done to allow an implementation to provide as much information as possible in the error code (for use with `MPI_ERROR_STRING`).

To make it possible for an application to interpret an error code, the routine `MPI_ERROR_CLASS` converts any error code into one of a small set of standard error codes, called *error classes*. Valid error classes are shown in Table 8.1 and Table 8.2.

The error classes are a subset of the error codes: an MPI function may return an error class number; and the function `MPI_ERROR_STRING` can be used to compute the error string associated with an error class. The values defined for MPI error classes are valid MPI error codes.

The error codes satisfy,

$$0 = \text{MPI\_SUCCESS} < \text{MPI\_ERR\_}\dots \leq \text{MPI\_ERR\_LASTCODE}.$$

*Rationale.* The difference between `MPI_ERR_UNKNOWN` and `MPI_ERR_OTHER` is that `MPI_ERROR_STRING` can return useful information about `MPI_ERR_OTHER`.

MPI_SUCCESS	No error
MPI_ERR_BUFFER	Invalid buffer pointer
MPI_ERR_COUNT	Invalid count argument
MPI_ERR_TYPE	Invalid datatype argument
MPI_ERR_TAG	Invalid tag argument
MPI_ERR_COMM	Invalid communicator
MPI_ERR_RANK	Invalid rank
MPI_ERR_REQUEST	Invalid request (handle)
MPI_ERR_ROOT	Invalid root
MPI_ERR_GROUP	Invalid group
MPI_ERR_OP	Invalid operation
MPI_ERR_TOPOLOGY	Invalid topology
MPI_ERR_DIMS	Invalid dimension argument
MPI_ERR_ARG	Invalid argument of some other kind
MPI_ERR_UNKNOWN	Unknown error
MPI_ERR_TRUNCATE	Message truncated on receive
MPI_ERR_OTHER	Known error not in this list
MPI_ERR_INTERN	Internal MPI (implementation) error
MPI_ERR_IN_STATUS	Error code is in status
MPI_ERR_PENDING	Pending request
MPI_ERR_KEYVAL	Invalid keyval has been passed
MPI_ERR_NO_MEM	MPI_ALLOC_MEM failed because memory is exhausted
MPI_ERR_BASE	Invalid base passed to MPI_FREE_MEM
MPI_ERR_INFO_KEY	Key longer than MPI_MAX_INFO_KEY
MPI_ERR_INFO_VALUE	Value longer than MPI_MAX_INFO_VAL
MPI_ERR_INFO_NOKEY	Invalid key passed to MPI_INFO_DELETE
MPI_ERR_SPAWN	Error in spawning processes
MPI_ERR_PORT	Invalid port name passed to MPI_COMM_CONNECT
MPI_ERR_SERVICE	Invalid service name passed to MPI_UNPUBLISH_NAME
MPI_ERR_NAME	Invalid service name passed to MPI_LOOKUP_NAME
MPI_ERR_WIN	Invalid win argument
MPI_ERR_SIZE	Invalid size argument
MPI_ERR_DISP	Invalid disp argument
MPI_ERR_INFO	Invalid info argument
MPI_ERR_LOCKTYPE	Invalid locktype argument
MPI_ERR_ASSERT	Invalid assert argument
MPI_ERR_RMA_CONFLICT	Conflicting accesses to window
MPI_ERR_RMA_SYNC	Wrong synchronization of RMA calls

Table 8.1: Error classes (Part 1)

MPI_ERR_RMA_RANGE	Target memory is not part of the window (in the case of a window created with MPI_WIN_CREATE_DYNAMIC, target memory is not attached)
MPI_ERR_RMA_ATTACH	Memory cannot be attached (e.g., because of resource exhaustion)
MPI_ERR_RMA_SHARED	Memory cannot be shared (e.g., some process in the group of the specified communicator cannot expose shared memory)
MPI_ERR_RMA_FLAVOR	Passed window has the wrong flavor for the called function
MPI_ERR_FILE	Invalid file handle
MPI_ERR_NOT_SAME	Collective argument not identical on all processes, or collective routines called in a different order by different processes
MPI_ERR_AMODE	Error related to the <code>amode</code> passed to MPI_FILE_OPEN
MPI_ERR_UNSUPPORTED_DATAREP	Unsupported <code>datarep</code> passed to MPI_FILE_SET_VIEW
MPI_ERR_UNSUPPORTED_OPERATION	Unsupported operation, such as seeking on a file which supports sequential access only
MPI_ERR_NO_SUCH_FILE	File does not exist
MPI_ERR_FILE_EXISTS	File exists
MPI_ERR_BAD_FILE	Invalid file name (e.g., path name too long)
MPI_ERR_ACCESS	Permission denied
MPI_ERR_NO_SPACE	Not enough space
MPI_ERR_QUOTA	Quota exceeded
MPI_ERR_READ_ONLY	Read-only file or file system
MPI_ERR_FILE_IN_USE	File operation could not be completed, as the file is currently open by some process
MPI_ERR_DUP_DATAREP	Conversion functions could not be registered because a data representation identifier that was already defined was passed to MPI_REGISTER_DATAREP
MPI_ERR_CONVERSION	An error occurred in a user supplied data conversion function.
MPI_ERR_IO	Other I/O error
MPI_ERR_LASTCODE	Last error code

Table 8.2: Error classes (Part 2)

Note that `MPI_SUCCESS = 0` is necessary to be consistent with C practice; the separation of error classes and error codes allows us to define the error classes this way. Having a known `LASTCODE` is often a nice sanity check as well. (*End of rationale.*)

```
MPI_ERROR_CLASS( errorcode, errorclass )
```

IN	errorcode	Error code returned by an MPI routine
OUT	errorclass	Error class associated with errorcode

```
int MPI_Error_class(int errorcode, int *errorclass)
```

```
MPI_Error_class(errorcode, errorclass, ierror)
```

```
    INTEGER, INTENT(IN) :: errorcode
```

```
    INTEGER, INTENT(OUT) :: errorclass
```

```
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_ERROR_CLASS(ERRORCODE, ERRORCLASS, IERROR)
```

```
    INTEGER ERRORCODE, ERRORCLASS, IERROR
```

The function `MPI_ERROR_CLASS` maps each standard error code (error class) onto itself.

## 8.5 Error Classes, Error Codes, and Error Handlers

Users may want to write a layered library on top of an existing MPI implementation, and this library may have its own set of error codes and classes. An example of such a library is an I/O library based on MPI, see Chapter 13. For this purpose, functions are needed to:

1. add a new error class to the ones an MPI implementation already knows.
2. associate error codes with this error class, so that `MPI_ERROR_CLASS` works.
3. associate strings with these error codes, so that `MPI_ERROR_STRING` works.
4. invoke the error handler associated with a communicator, window, or object.

Several functions are provided to do this. They are all local. No functions are provided to free error classes or codes: it is not expected that an application will generate them in significant numbers.

```
MPI_ADD_ERROR_CLASS(errorclass)
```

OUT	errorclass	value for the new error class (integer)
-----	------------	---

```
int MPI_Add_error_class(int *errorclass)
```

```
MPI_Add_error_class(errorclass, ierror)
```

```
    INTEGER, INTENT(OUT) :: errorclass
```

```
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

`MPI_ADD_ERROR_CLASS(ERRORCLASS, IERROR)`

INTEGER ERRORCLASS, IERROR

Creates a new error class and returns the value for it.

*Rationale.* To avoid conflicts with existing error codes and classes, the value is set by the implementation and not by the user. (*End of rationale.*)

*Advice to implementors.* A high-quality implementation will return the value for a new `errorclass` in the same deterministic way on all processes. (*End of advice to implementors.*)

*Advice to users.* Since a call to `MPI_ADD_ERROR_CLASS` is local, the same `errorclass` may not be returned on all processes that make this call. Thus, it is not safe to assume that registering a new error on a set of processes at the same time will yield the same `errorclass` on all of the processes. However, if an implementation returns the new `errorclass` in a deterministic way, and they are always generated in the same order on the same set of processes (for example, all processes), then the value will be the same. However, even if a deterministic algorithm is used, the value can vary across processes. This can happen, for example, if different but overlapping groups of processes make a series of calls. As a result of these issues, getting the “same” error on multiple processes may not cause the same value of error code to be generated. (*End of advice to users.*)

The value of `MPI_ERR_LASTCODE` is a constant value and is not affected by new user-defined error codes and classes. Instead, a predefined attribute key `MPI_LASTUSED` is associated with `MPI_COMM_WORLD`. The attribute value corresponding to this key is the current maximum error class including the user-defined ones. This is a local value and may be different on different processes. The value returned by this key is always greater than or equal to `MPI_ERR_LASTCODE`.

*Advice to users.* The value returned by the key `MPI_LASTUSED` will not change unless the user calls a function to explicitly add an error class/code. In a multi-threaded environment, the user must take extra care in assuming this value has not changed. Note that error codes and error classes are not necessarily dense. A user may not assume that each error class below `MPI_LASTUSED` is valid. (*End of advice to users.*)

`MPI_ADD_ERROR_CODE(errorclass, errorcode)`

IN            errorclass                            error class (integer)

OUT          errorcode                            new error code to associated with errorclass (integer)

`int MPI_Add_error_code(int errorclass, int *errorcode)`

`MPI_Add_error_code(errorclass, errorcode, ierror)`

INTEGER, INTENT(IN) :: errorclass

INTEGER, INTENT(OUT) :: errorcode

```

1      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
3  MPI_ADD_ERROR_CODE(ERRORCLASS, ERRORCODE, IERROR)
4      INTEGER ERRORCLASS, ERRORCODE, IERROR

```

Creates new error code associated with `errorclass` and returns its value in `errorcode`.

*Rationale.* To avoid conflicts with existing error codes and classes, the value of the new error code is set by the implementation and not by the user. (*End of rationale.*)

*Advice to implementors.* A high-quality implementation will return the value for a new `errorcode` in the same deterministic way on all processes. (*End of advice to implementors.*)

```

15  MPI_ADD_ERROR_STRING(errorcode, string)
16
17      IN          errorcode          error code or class (integer)
18      IN          string             text corresponding to errorcode (string)

```

```

20  int MPI_Add_error_string(int errorcode, const char *string)

```

```

22  MPI_Add_error_string(errorcode, string, ierror)
23      INTEGER, INTENT(IN) :: errorcode
24      CHARACTER(LEN=*), INTENT(IN) :: string
25      INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

26  MPI_ADD_ERROR_STRING(ERRORCODE, STRING, IERROR)
27      INTEGER ERRORCODE, IERROR
28      CHARACTER*(*) STRING

```

Associates an error string with an error code or class. The string must be no more than `MPI_MAX_ERROR_STRING` characters long. The length of the string is as defined in the calling language. The length of the string does not include the null terminator in C. Trailing blanks will be stripped in Fortran. Calling `MPI_ADD_ERROR_STRING` for an `errorcode` that already has a string will replace the old string with the new string. It is erroneous to call `MPI_ADD_ERROR_STRING` for an error code or class with a value  $\leq$  `MPI_ERR_LASTCODE`.

If `MPI_ERROR_STRING` is called when no string has been set, it will return a empty string (all spaces in Fortran, "" in C).

Section 8.3 describes the methods for creating and associating error handlers with communicators, files, and windows.

```

41  MPI_COMM_CALL_ERRHANDLER (comm, errorcode)
42
43      IN          comm              communicator with error handler (handle)
44      IN          errorcode         error code (integer)

```

```

46  int MPI_Comm_call_errhandler(MPI_Comm comm, int errorcode)

```

```

48  MPI_Comm_call_errhandler(comm, errorcode, ierror)

```

```

    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_COMM_CALL_ERRHANDLER(COMM, ERRORCODE, IERROR)
    INTEGER COMM, ERRORCODE, IERROR

```

This function invokes the error handler assigned to the communicator with the error code supplied. This function returns `MPI_SUCCESS` in C and the same value in `IERROR` if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

*Advice to users.* Users should note that the default error handler is `MPI_ERRORS_ARE_FATAL`. Thus, calling `MPI_COMM_CALL_ERRHANDLER` will abort the `comm` processes if the default error handler has not been changed for this communicator or on the parent before the communicator was created. (*End of advice to users.*)

```

MPI_WIN_CALL_ERRHANDLER (win, errorcode)
    IN      win                window with error handler (handle)
    IN      errorcode          error code (integer)

```

```

int MPI_Win_call_errhandler(MPI_Win win, int errorcode)
MPI_Win_call_errhandler(win, errorcode, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

MPI_WIN_CALL_ERRHANDLER(WIN, ERRORCODE, IERROR)
    INTEGER WIN, ERRORCODE, IERROR

```

This function invokes the error handler assigned to the window with the error code supplied. This function returns `MPI_SUCCESS` in C and the same value in `IERROR` if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

*Advice to users.* As with communicators, the default error handler for windows is `MPI_ERRORS_ARE_FATAL`. (*End of advice to users.*)

```

MPI_FILE_CALL_ERRHANDLER (fh, errorcode)
    IN      fh                file with error handler (handle)
    IN      errorcode          error code (integer)

```

```

int MPI_File_call_errhandler(MPI_File fh, int errorcode)

```

```

1 MPI_File_call_errhandler(fh, errorcode, ierror)
2     TYPE(MPI_File), INTENT(IN) :: fh
3     INTEGER, INTENT(IN) :: errorcode
4     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
6 MPI_FILE_CALL_ERRHANDLER(FH, ERRORCODE, IERROR)
7     INTEGER FH, ERRORCODE, IERROR

```

This function invokes the error handler assigned to the file with the error code supplied. This function returns `MPI_SUCCESS` in C and the same value in `IERROR` if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

*Advice to users.* Unlike errors on communicators and windows, the default behavior for files is to have `MPI_ERRORS_RETURN`. (*End of advice to users.*)

*Advice to users.* Users are warned that handlers should not be called recursively with `MPI_COMM_CALL_ERRHANDLER`, `MPI_FILE_CALL_ERRHANDLER`, or `MPI_WIN_CALL_ERRHANDLER`. Doing this can create a situation where an infinite recursion is created. This can occur if `MPI_COMM_CALL_ERRHANDLER`, `MPI_FILE_CALL_ERRHANDLER`, or `MPI_WIN_CALL_ERRHANDLER` is called inside an error handler.

Error codes and classes are associated with a process. As a result, they may be used in any error handler. Error handlers should be prepared to deal with any error code they are given. Furthermore, it is good practice to only call an error handler with the appropriate error codes. For example, file errors would normally be sent to the file error handler. (*End of advice to users.*)

## 8.6 Timers and Synchronization

MPI defines a timer. A timer is specified even though it is not “message-passing,” because timing parallel programs is important in “performance debugging” and because existing timers (both in POSIX 1003.1-1988 and 1003.4D 14.1 and in Fortran 90) are either inconvenient or do not provide adequate access to high resolution timers. See also Section 2.6.4.

```

35 MPI_WTIME()
36
37 double MPI_Wtime(void)
38
39 DOUBLE PRECISION MPI_Wtime()
40
41 DOUBLE PRECISION MPI_WTIME()

```

`MPI_WTIME` returns a floating-point number of seconds, representing elapsed wall-clock time since some time in the past.

The “time in the past” is guaranteed not to change during the life of the process. The user is responsible for converting large numbers of seconds to other units if they are preferred.

This function is portable (it returns seconds, not “ticks”), it allows high-resolution, and carries no unnecessary baggage. One would use it like this:



```

{
    double starttime, endtime;
    starttime = MPI_Wtime();
    .... stuff to be timed ...
    endtime = MPI_Wtime();
    printf("That took %f seconds\n",endtime-starttime);
}

```

The times returned are local to the node that called them. There is no requirement that different nodes return “the same time.” (But see also the discussion of `MPI_WTIME_IS_GLOBAL` in Section 8.1.2).

`MPI_WTICK()`

```

double MPI_Wtick(void)
DOUBLE PRECISION MPI_Wtick()
DOUBLE PRECISION MPI_WTICK()

```

`MPI_WTICK` returns the resolution of `MPI_WTIME` in seconds. That is, it returns, as a double precision value, the number of seconds between successive clock ticks. For example, if the clock is implemented by the hardware as a counter that is incremented every millisecond, the value returned by `MPI_WTICK` should be  $10^{-3}$ .

## 8.7 Startup

One goal of MPI is to achieve *source code portability*. By this we mean that a program written using MPI and complying with the relevant language standards is portable as written, and must not require any source code changes when moved from one system to another. This explicitly does *not* say anything about how an MPI program is started or launched from the command line, nor what the user must do to set up the environment in which an MPI program will run. However, an implementation may require some setup to be performed before other MPI routines may be called. To provide for this, MPI includes an initialization routine `MPI_INIT`.

`MPI_INIT()`

```

int MPI_Init(int *argc, char ***argv)
MPI_Init(ierror)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_INIT(IERROR)
    INTEGER IERROR

```

All MPI programs must contain exactly one call to an MPI initialization routine: `MPI_INIT` or `MPI_INIT_THREAD`. Subsequent calls to any initialization routines are erroneous. The only MPI functions that may be invoked before the MPI initialization routines

are called are `MPI_GET_VERSION`, `MPI_GET_LIBRARY_VERSION`, `MPI_INITIALIZED`, `MPI_FINALIZED`, and any function with the prefix `MPI_T_` (within the constraints for functions with this prefix listed in Section 14.3.4). The version for ISO C accepts the `argc` and `argv` that are provided by the arguments to `main` or `NULL`:

```

1  int main(int argc, char *argv[])
2  {
3      MPI_Init(&argc, &argv);
4
5      /* parse arguments */
6      /* main program    */
7
8      MPI_Finalize();    /* see below */
9      return 0;
10 }

```

The Fortran version takes only `IERROR`.

Conforming implementations of MPI are required to allow applications to pass `NULL` for both the `argc` and `argv` arguments of `main` in C.

After MPI is initialized, the application can access information about the execution environment by querying the predefined info object `MPI_INFO_ENV`. The following keys are predefined for this object, corresponding to the arguments of `MPI_COMM_SPAWN` or of `mpiexec`:

`command` Name of program executed.

`argv` Space separated arguments to command.

`maxprocs` Maximum number of MPI processes to start.

`soft` Allowed values for number of processors.

`host` Hostname.

`arch` Architecture name.

`wdir` Working directory of the MPI process.

`file` Value is the name of a file in which additional information is specified.

`thread_level` Requested level of thread support, if requested before the program started execution.

Note that all values are strings. Thus, the maximum number of processes is represented by a string such as “1024” and the requested level is represented by a string such as “MPI\_THREAD\_SINGLE”.

The info object `MPI_INFO_ENV` need not contain a (key,value) pair for each of these predefined keys; the set of (key,value) pairs provided is implementation-dependent. Implementations may provide additional, implementation specific, (key,value) pairs.

In case where the MPI processes were started with `MPI_COMM_SPAWN_MULTIPLE` or, equivalently, with a startup mechanism that supports multiple process specifications,

then the values stored in the info object `MPI_INFO_ENV` at a process are those values that affect the local MPI process.

**Example 8.4** If MPI is started with a call to

```
mpirun -n 5 -arch sun ocean : -n 10 -arch rs6000 atmos
```

Then the first 5 processes will have in their `MPI_INFO_ENV` object the pairs (command, ocean), (maxprocs, 5), and (arch, sun). The next 10 processes will have in `MPI_INFO_ENV` (command, atmos), (maxprocs, 10), and (arch, rs6000)

*Advice to users.* The values passed in `MPI_INFO_ENV` are the values of the arguments passed to the mechanism that started the MPI execution — not the actual value provided. Thus, the value associated with `maxprocs` is the number of MPI processes requested; it can be larger than the actual number of processes obtained, if the `soft` option was used. (*End of advice to users.*)

*Advice to implementors.* High-quality implementations will provide a (key,value) pair for each parameter that can be passed to the command that starts an MPI program. (*End of advice to implementors.*)

## MPI\_FINALIZE()

```
int MPI_Finalize(void)
```

```
MPI_Finalize(ierr)
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierr
```

```
MPI_FINALIZE(IERROR)
```

```
INTEGER IERROR
```

This routine cleans up all MPI state. If an MPI program terminates normally (i.e., not due to a call to `MPI_ABORT` or an unrecoverable error) then each process must call `MPI_FINALIZE` before it exits.

Before an MPI process invokes `MPI_FINALIZE`, the process must perform all MPI calls needed to complete its involvement in MPI communications: It must locally complete all MPI operations that it initiated and must execute matching calls needed to complete MPI communications initiated by other processes. For example, if the process executed a non-blocking send, it must eventually call `MPI_WAIT`, `MPI_TEST`, `MPI_REQUEST_FREE`, or any derived function; if the process is the target of a send, then it must post the matching receive; if it is part of a group executing a collective operation, then it must have completed its participation in the operation.

The call to `MPI_FINALIZE` does not free objects created by MPI calls; these objects are freed using `MPI_XXX_FREE` calls.

`MPI_FINALIZE` is collective over all connected processes. If no processes were spawned, accepted or connected then this means over `MPI_COMM_WORLD`; otherwise it is collective over the union of all processes that have been and continue to be connected, as explained in Section 10.5.4.

The following examples illustrates these rules

**Example 8.5** The following code is correct

Process 0	Process 1
-----	-----
MPI_Init();	MPI_Init();
MPI_Send(dest=1);	MPI_Recv(src=0);
MPI_Finalize();	MPI_Finalize();

**Example 8.6** Without a matching receive, the program is erroneous

Process 0	Process 1
-----	-----
MPI_Init();	MPI_Init();
MPI_Send (dest=1);	
MPI_Finalize();	MPI_Finalize();

**Example 8.7** This program is correct: Process 0 calls MPI\_Finalize after it has executed the MPI calls that complete the send operation. Likewise, process 1 executes the MPI call that completes the matching receive operation before it calls MPI\_Finalize.

Process 0	Process 1
-----	-----
MPI_Init();	MPI_Init();
MPI_Isend(dest=1);	MPI_Recv(src=0);
MPI_Request_free();	MPI_Finalize();
MPI_Finalize();	exit();
exit();	

**Example 8.8** This program is correct. The attached buffer is a resource allocated by the user, not by MPI; it is available to the user after MPI is finalized.

Process 0	Process 1
-----	-----
MPI_Init();	MPI_Init();
buffer = malloc(1000000);	MPI_Recv(src=0);
MPI_Buffer_attach();	MPI_Finalize();
MPI_Send(dest=1));	exit();
MPI_Finalize();	
free(buffer);	
exit();	

**Example 8.9** This program is correct. The cancel operation must succeed, since the send cannot complete normally. The wait operation, after the call to MPI\_Cancel, is local — no matching MPI call is required on process 1.

Process 0	Process 1
-----	-----
MPI_Issend(dest=1);	MPI_Finalize();
MPI_Cancel();	
MPI_Wait();	
MPI_Finalize();	

*Advice to implementors.* Even though a process has executed all MPI calls needed to complete the communications it is involved with, such communication may not yet be completed from the viewpoint of the underlying MPI system. For example, a blocking send may have returned, even though the data is still buffered at the sender in an MPI buffer; an MPI process may receive a cancel request for a message it has completed receiving. The MPI implementation must ensure that a process has completed any involvement in MPI communication before MPI\_FINALIZE returns. Thus, if a process exits after the call to MPI\_FINALIZE, this will not cause an ongoing communication to fail. The MPI implementation should also complete freeing all objects marked for deletion by MPI calls that freed them. (*End of advice to implementors.*)

Once MPI\_FINALIZE returns, no MPI routine (not even MPI\_INIT) may be called, except for MPI\_GET\_VERSION, MPI\_GET\_LIBRARY\_VERSION, MPI\_INITIALIZED, MPI\_FINALIZED, and any function with the prefix MPI\_T\_ (within the constraints for functions with this prefix listed in Section 14.3.4).

Although it is not required that all processes return from MPI\_FINALIZE, it is required that at least process 0 in MPI\_COMM\_WORLD return, so that users can know that the MPI portion of the computation is over. In addition, in a POSIX environment, users may desire to supply an exit code for each process that returns from MPI\_FINALIZE.

**Example 8.10** The following illustrates the use of requiring that at least one process return and that it be known that process 0 is one of the processes that return. One wants code like the following to work no matter how many processes return.

```

...
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
...
MPI_Finalize();
if (myrank == 0) {
    resultfile = fopen("outfile","w");
    dump_results(resultfile);
    fclose(resultfile);
}
exit(0);

```

MPI\_INITIALIZED(flag)

OUT      flag

Flag is true if MPI\_INIT has been called and false otherwise.

int MPI\_Initialized(int \*flag)

```

1 MPI_Initialized(flag, ierror)
2     LOGICAL, INTENT(OUT) :: flag
3     INTEGER, OPTIONAL, INTENT(OUT) :: ierror

```

```

4 MPI_INITIALIZED(FLAG, IERROR)
5     LOGICAL FLAG
6     INTEGER IERROR
7

```

This routine may be used to determine whether MPI\_INIT has been called. MPI\_INITIALIZED returns true if the calling process has called MPI\_INIT. Whether MPI\_FINALIZE has been called does not affect the behavior of MPI\_INITIALIZED. It is one of the few routines that may be called before MPI\_INIT is called. This function is callable from threads without restriction, see Section 12.4.

```

14 MPI_ABORT(comm, errorcode)
15

```

```

16     IN          comm          communicator of tasks to abort
17     IN          errorcode     error code to return to invoking environment
18

```

```

19 int MPI_Abort(MPI_Comm comm, int errorcode)
20

```

```

21 MPI_Abort(comm, errorcode, ierror)
22     TYPE(MPI_Comm), INTENT(IN) :: comm
23     INTEGER, INTENT(IN) :: errorcode
24     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
25

```

```

26 MPI_ABORT(COMM, ERRORCODE, IERROR)
27     INTEGER COMM, ERRORCODE, IERROR
28

```

This routine makes a “best attempt” to abort all tasks in the group of `comm`. This function does not require that the invoking environment take any action with the error code. However, a Unix or POSIX environment should handle this as a **return errorcode** from the main program.

It may not be possible for an MPI implementation to abort only the processes represented by `comm` if this is a subset of the processes. In this case, the MPI implementation should attempt to abort all the connected processes but should not abort any unconnected processes. If no processes were spawned, accepted, or connected then this has the effect of aborting all the processes associated with MPI\_COMM\_WORLD.

*Rationale.* The communicator argument is provided to allow for future extensions of MPI to environments with, for example, dynamic process management. In particular, it allows but does not require an MPI implementation to abort a subset of MPI\_COMM\_WORLD. (*End of rationale.*)

*Advice to users.* Whether the `errorcode` is returned from the executable or from the MPI process startup mechanism (e.g., `mpiexec`), is an aspect of quality of the MPI library but not mandatory. (*End of advice to users.*)

*Advice to implementors.* Where possible, a high-quality implementation will try to return the `errorcode` from the MPI process startup mechanism (e.g. `mpiexec` or singleton init). (*End of advice to implementors.*)

### 8.7.1 Allowing User Functions at Process Termination

There are times in which it would be convenient to have actions happen when an MPI process finishes. For example, a routine may do initializations that are useful until the MPI job (or that part of the job that being terminated in the case of dynamically created processes) is finished. This can be accomplished in MPI by attaching an attribute to `MPI_COMM_SELF` with a callback function. When `MPI_FINALIZE` is called, it will first execute the equivalent of an `MPI_COMM_FREE` on `MPI_COMM_SELF`. This will cause the delete callback function to be executed on all keys associated with `MPI_COMM_SELF`, in the reverse order that they were set on `MPI_COMM_SELF`. If no key has been attached to `MPI_COMM_SELF`, then no callback is invoked. The “freeing” of `MPI_COMM_SELF` occurs before any other parts of MPI are affected. Thus, for example, calling `MPI_FINALIZED` will return false in any of these callback functions. Once done with `MPI_COMM_SELF`, the order and rest of the actions taken by `MPI_FINALIZE` is not specified.

*Advice to implementors.* Since attributes can be added from any supported language, the MPI implementation needs to remember the creating language so the correct callback is made. Implementations that use the attribute delete callback on MPI\_COMM\_SELF internally should register their internal callbacks before returning from MPI\_INIT / MPI\_INIT\_THREAD, so that libraries or applications will not have portions of the MPI implementation shut down before the application-level callbacks are made. (*End of advice to implementors.*)

### 8.7.2 Determining Whether MPI Has Finished

One of the goals of MPI was to allow for layered libraries. In order for a library to do this cleanly, it needs to know if MPI is active. In MPI the function `MPI_INITIALIZED` was provided to tell if MPI had been initialized. The problem arises in knowing if MPI has been finalized. Once MPI has been finalized it is no longer active and cannot be restarted. A library needs to be able to determine this to act accordingly. To achieve this the following function is needed:

MPI\_FINALIZED(flag)

OUT	flag	true if MPI was finalized (logical)
-----	------	-------------------------------------

```
int MPI_Finalized(int *flag)
```

```
MPI_Finalized(flag, ierror)
```

```
LOGICAL, INTENT(OUT) :: flag
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

MPI\_FINALIZED(FLAG, IERROR)

LOGICAL FLAG

INTEGER IERROR

This routine returns `true` if `MPI_FINALIZE` has completed. It is valid to call `MPI_FINALIZED` before `MPI_INIT` and after `MPI_FINALIZE`. This function is callable from threads without restriction, see Section 12.4.

*Advice to users.* MPI is “active” and it is thus safe to call MPI functions if MPI\_INIT has completed and MPI\_FINALIZE has not completed. If a library has no other way of knowing whether MPI is active or not, then it can use MPI\_INITIALIZED and MPI\_FINALIZED to determine this. For example, MPI is “active” in callback functions that are invoked during MPI\_FINALIZE. (*End of advice to users.*)

## 8.8 Portable MPI Process Startup

A number of implementations of MPI provide a startup command for MPI programs that is of the form

```
mpirun <mpirun arguments> <program> <program arguments>
```

Separating the command to start the program from the program itself provides flexibility, particularly for network and heterogeneous implementations. For example, the startup script need not run on one of the machines that will be executing the MPI program itself.

Having a standard startup mechanism also extends the portability of MPI programs one step further, to the command lines and scripts that manage them. For example, a validation suite script that runs hundreds of programs can be a portable script if it is written using such a standard startup mechanism. In order that the “standard” command not be confused with existing practice, which is not standard and not portable among implementations, instead of `mpirun` MPI specifies `mpiexec`.

While a standardized startup mechanism improves the usability of MPI, the range of environments is so diverse (e.g., there may not even be a command line interface) that MPI cannot mandate such a mechanism. Instead, MPI specifies an `mpiexec` startup command and recommends but does not require it, as advice to implementors. However, if an implementation does provide a command called `mpiexec`, it must be of the form described below.

It is suggested that

```
mpiexec -n <numprocs> <program>
```

be at least one way to start `<program>` with an initial MPI\_COMM\_WORLD whose group contains `<numprocs>` processes. Other arguments to `mpiexec` may be implementation-dependent.

*Advice to implementors.* Implementors, if they do provide a special startup command for MPI programs, are advised to give it the following form. The syntax is chosen in order that `mpiexec` be able to be viewed as a command-line version of MPI\_COMM\_SPAWN (See Section 10.3.4).

Analogous to MPI\_COMM\_SPAWN, we have

```
mpiexec -n    <maxprocs>
           -soft <      >
           -host <      >
           -arch <      >
           -wdir <      >
           -path <      >
           -file <      >
```



```
...
<command line>
```

for the case where a single command line for the application program and its arguments will suffice. See Section 10.3.4 for the meanings of these arguments. For the case corresponding to MPI\_COMM\_SPAWN\_MULTIPLE there are two possible formats:

Form A:

```
mpiexec { <above arguments> } : { ... } : { ... } : ... : { ... }
```

As with MPI\_COMM\_SPAWN, all the arguments are optional. (Even the `-n x` argument is optional; the default is implementation dependent. It might be 1, it might be taken from an environment variable, or it might be specified at compile time.) The names and meanings of the arguments are taken from the keys in the `info` argument to MPI\_COMM\_SPAWN. There may be other, implementation-dependent arguments as well.

Note that Form A, though convenient to type, prevents colons from being program arguments. Therefore an alternate, file-based form is allowed:

Form B:

```
mpiexec -configfile <filename>
```

where the lines of `<filename>` are of the form separated by the colons in Form A. Lines beginning with `#` are comments, and lines may be continued by terminating the partial line with `\`.

**Example 8.11** Start 16 instances of `myprog` on the current or default machine:

```
mpiexec -n 16 myprog
```

**Example 8.12** Start 10 processes on the machine called `ferrari`:

```
mpiexec -n 10 -host ferrari myprog
```

**Example 8.13** Start three copies of the same program with different command-line arguments:

```
mpiexec myprog infile1 : myprog infile2 : myprog infile3
```

**Example 8.14** Start the `ocean` program on five Suns and the `atmos` program on 10 RS/6000's:

```
mpiexec -n 5 -arch sun ocean : -n 10 -arch rs6000 atmos
```

It is assumed that the implementation in this case has a method for choosing hosts of the appropriate type. Their ranks are in the order specified.

**Example 8.15** Start the `ocean` program on five Suns and the `atmos` program on 10 RS/6000's (Form B):

```
mpiexec -configfile myfile
```

where `myfile` contains

```
-n 5 -arch sun    ocean  
-n 10 -arch rs6000 atmos
```

*(End of advice to implementors.)*

# Index

MPI exception, 8

CONST:(arch, rs6000), 25  
CONST:(arch, sun), 25  
CONST:(command, atmos), 25  
CONST:(command, ocean), 25  
CONST:(maxprocs, 10), 25  
CONST:(maxprocs, 5), 25  
CONST:\_WORLD, 8  
CONST:XXX, 9  
CONST:“1024”, 24  
CONST:“MPI\_THREAD\_SINGLE”, 24  
CONST:arch, 24  
CONST:argv, 24  
CONST:CHARACTER\*(\*), 15  
CONST:COMM, 9  
CONST:command, 24  
CONST:errorcode, 15, 18  
CONST:FILE, 9  
CONST:file, 24  
CONST:host, 24  
CONST:IERROR, 24  
CONST:LASTCODE, 18  
CONST:maxprocs, 24, 25  
CONST:MPI\_ANY\_SOURCE, 3  
CONST:MPI\_COMM-, 8  
CONST:MPI\_COMM\_SELF, 29  
CONST:MPI\_COMM\_WORLD, 2–4, 8, 10, 19, 25, 27, 28, 30  
CONST:MPI\_ERR\_..., 15  
CONST:MPI\_ERR\_ACCESS, 17  
CONST:MPI\_ERR\_AMODE, 17  
CONST:MPI\_ERR\_ARG, 16  
CONST:MPI\_ERR\_ASSERT, 16  
CONST:MPI\_ERR\_BAD\_FILE, 17  
CONST:MPI\_ERR\_BASE, 6, 16  
CONST:MPI\_ERR\_BUFFER, 16  
CONST:MPI\_ERR\_COMM, 16  
CONST:MPI\_ERR\_CONVERSION, 17  
CONST:MPI\_ERR\_COUNT, 16  
CONST:MPI\_ERR\_DIMS, 16  
CONST:MPI\_ERR\_DISP, 16  
CONST:MPI\_ERR\_DUP\_DATAREP, 17  
CONST:MPI\_ERR\_FILE, 17  
CONST:MPI\_ERR\_FILE\_EXISTS, 17  
CONST:MPI\_ERR\_FILE\_IN\_USE, 17  
CONST:MPI\_ERR\_GROUP, 16  
CONST:MPI\_ERR\_IN\_STATUS, 10, 16  
CONST:MPI\_ERR\_INFO, 16  
CONST:MPI\_ERR\_INFO\_KEY, 16  
CONST:MPI\_ERR\_INFO\_NOKEY, 16  
CONST:MPI\_ERR\_INFO\_VALUE, 16  
CONST:MPI\_ERR\_INTERN, 16  
CONST:MPI\_ERR\_IO, 17  
CONST:MPI\_ERR\_KEYVAL, 16  
CONST:MPI\_ERR\_LASTCODE, 15, 17, 19, 20  
CONST:MPI\_ERR\_LOCKTYPE, 16  
CONST:MPI\_ERR\_NAME, 16  
CONST:MPI\_ERR\_NO\_MEM, 6, 16  
CONST:MPI\_ERR\_NO\_SPACE, 17  
CONST:MPI\_ERR\_NO\_SUCH\_FILE, 17  
CONST:MPI\_ERR\_NOT\_SAME, 17  
CONST:MPI\_ERR\_OP, 16  
CONST:MPI\_ERR\_OTHER, 15, 16  
CONST:MPI\_ERR\_PENDING, 16  
CONST:MPI\_ERR\_PORT, 16  
CONST:MPI\_ERR\_QUOTA, 17  
CONST:MPI\_ERR\_RANK, 16  
CONST:MPI\_ERR\_READ\_ONLY, 17  
CONST:MPI\_ERR\_REQUEST, 16  
CONST:MPI\_ERR\_RMA\_ATTACH, 17  
CONST:MPI\_ERR\_RMA\_CONFLICT, 16  
CONST:MPI\_ERR\_RMA\_FLAVOR, 17  
CONST:MPI\_ERR\_RMA\_RANGE, 17  
CONST:MPI\_ERR\_RMA\_SHARED, 17  
CONST:MPI\_ERR\_RMA\_SYNC, 16  
CONST:MPI\_ERR\_ROOT, 16  
CONST:MPI\_ERR\_SERVICE, 16  
CONST:MPI\_ERR\_SIZE, 16

1 [CONST:MPI\\_ERR\\_SPAWN, 16](#)  
 2 [CONST:MPI\\_ERR\\_TAG, 16](#)  
 3 [CONST:MPI\\_ERR\\_TOPOLOGY, 16](#)  
 4 [CONST:MPI\\_ERR\\_TRUNCATE, 16](#)  
 5 [CONST:MPI\\_ERR\\_TYPE, 16](#)  
 6 [CONST:MPI\\_ERR\\_UNKNOWN, 15, 16](#)  
 7 [CONST:MPI\\_ERR\\_UNSUPPORTED\\_DATA, 17](#)  
 8 [CONST:MPI\\_ERR\\_UNSUPPORTED\\_OPERATION, 17](#)  
 9 [CONST:MPI\\_ERR\\_WIN, 16](#)  
 10 [CONST:MPI\\_Errhandler, 9, 10–14](#)  
 11 [CONST:MPI\\_ERRHANDLER\\_NULL, 14](#)  
 12 [CONST:MPI\\_ERRORS\\_ARE\\_FATAL, 8, 9, 21](#)  
 13 [CONST:MPI\\_ERRORS\\_RETURN, 8, 9, 22](#)  
 14 [CONST:MPI\\_File, 13, 14, 21](#)  
 15 [CONST:MPI\\_HOST, 3](#)  
 16 [CONST:MPI\\_Info, 5](#)  
 17 [CONST:MPI\\_INFO\\_ENV, 24, 25](#)  
 18 [CONST:MPI\\_IO, 3](#)  
 19 [CONST:MPI\\_LASTUSED\\_CODE, 19](#)  
 20 [CONST:MPI\\_MAX\\_ERROR\\_STRING, 15, 20](#)  
 21 [CONST:MPI\\_MAX\\_INFO\\_KEY, 16](#)  
 22 [CONST:MPI\\_MAX\\_INFO\\_VAL, 16](#)  
 23 [CONST:MPI\\_MAX\\_LIBRARY\\_VERSION\\_STRING, 2](#)  
 24 [CONST:MPI\\_MAX\\_PROCESSOR\\_NAME, 4, 5](#)  
 25 [CONST:MPI\\_PROC\\_NULL, 3](#)  
 26 [CONST:MPI\\_SUBVERSION, 2](#)  
 27 [CONST:MPI\\_SUCCESS, 15, 16, 18, 21, 22](#)  
 28 [CONST:MPI\\_TAG\\_UB, 3](#)  
 29 [CONST:MPI\\_VERSION, 2](#)  
 30 [CONST:MPI\\_Win, 12, 21](#)  
 31 [CONST:MPI\\_WTIME\\_IS\\_GLOBAL, 3, 4, 23](#)  
 32 [CONST:PRINT, 15](#)  
 33 [CONST:soft, 24, 25](#)  
 34 [CONST:string, 15](#)  
 35 [CONST:thread\\_level, 24](#)  
 36 [CONST:void\\*, 6](#)  
 37 [CONST:wdir, 24](#)  
 38 [CONST:WIN, 9](#)  
 39 [EXAMPLES:MPI\\_ALLOC\\_MEM, 7](#)  
 40 [EXAMPLES:MPI\\_Alloc\\_mem, 7](#)  
 41 [EXAMPLES:MPI\\_Barrier, 26](#)  
 42 [EXAMPLES:MPI\\_Buffer\\_attach, 26](#)  
 43 [EXAMPLES:MPI\\_Cancel, 26](#)  
 44 [EXAMPLES:MPI\\_Finalize, 26, 27](#)  
 45 [EXAMPLES:MPI\\_FREE\\_MEM, 7](#)  
 46 [EXAMPLES:MPI\\_INFO\\_ENV, 25](#)  
 47 [EXAMPLES:MPI\\_Iprobe, 26](#)  
 48 [EXAMPLES:MPI\\_Request\\_free, 26](#)  
 49 [EXAMPLES:MPI\\_Test\\_cancelled, 26](#)  
 50 [EXAMPLES:mpiexec, 25, 31, 32](#)  
 51 [HOST, 3](#)  
 52 [MPI\\_ABORT, 8, 25](#)  
 53 [MPI\\_ABORT\(comm, errorcode\), 28](#)  
 54 [MPI\\_ADD\\_ERROR\\_CLASS, 19](#)  
 55 [MPI\\_ADD\\_ERROR\\_CLASS\(errorclass\), 18](#)  
 56 [MPI\\_ADD\\_ERROR\\_CODE\(errorclass, error-  
 57 code\), 19](#)  
 58 [MPI\\_ADD\\_ERROR\\_STRING, 20](#)  
 59 [MPI\\_ADD\\_ERROR\\_STRING\(errorcode, string\),  
 60 20](#)  
 61 [MPI\\_ALLOC\\_MEM, 6, 7, 16](#)  
 62 [MPI\\_ALLOC\\_MEM\(size, info, baseptr\), 5](#)  
 63 [MPI\\_ALLOC\\_MEM\\_CPTR, 6](#)  
 64 [MPI\\_CANCEL, 26](#)  
 65 [MPI\\_COMM\\_CALL\\_ERRHANDLER, 22](#)  
 66 [MPI\\_COMM\\_CALL\\_ERRHANDLER\(comm,  
 67 errorcode\), 20](#)  
 68 [MPI\\_COMM\\_CONNECT, 16](#)  
 69 [MPI\\_COMM\\_CREATE\\_ERRHANDLER, 9,  
 70 11](#)  
 71 [MPI\\_COMM\\_CREATE\\_ERRHANDLER\(comm\\_errhandler\\_fn,  
 72 errhandler\), 9](#)  
 73 [MPI\\_COMM\\_FREE, 25, 29](#)  
 74 [MPI\\_COMM\\_GET\\_ATTR, 2](#)  
 75 [MPI\\_COMM\\_GET\\_ERRHANDLER, 9](#)  
 76 [MPI\\_COMM\\_GET\\_ERRHANDLER\(comm,  
 77 errhandler\), 11](#)  
 78 [MPI\\_COMM\\_GROUP, 9](#)  
 79 [MPI\\_COMM\\_SET\\_ERRHANDLER, 9](#)  
 80 [MPI\\_COMM\\_SET\\_ERRHANDLER\(comm, er-  
 81 rhandler\), 10](#)  
 82 [MPI\\_COMM\\_SPAWN, 24, 30, 31](#)  
 83 [MPI\\_COMM\\_SPAWN\\_MULTIPLE, 24, 31](#)  
 84 [MPI\\_ERRHANDLER\\_FREE, 9, 25](#)  
 85 [MPI\\_ERRHANDLER\\_FREE\( errhandler \),  
 86 14](#)  
 87 [MPI\\_ERROR\\_CLASS, 15, 18](#)

MPI_ERROR_CLASS( errorcode, errorclass ), <a href="#">18</a>	MPI_UNPUBLISH_NAME, <a href="#">16</a>	1
MPI_ERROR_STRING, <a href="#">15</a> , <a href="#">18</a> , <a href="#">20</a>	MPI_WAIT, <a href="#">25</a>	2
MPI_ERROR_STRING( errorcode, string, resultlen ), <a href="#">15</a>	MPI_WIN_CALL_ERRHANDLER, <a href="#">22</a>	3
MPI_FILE_CALL_ERRHANDLER, <a href="#">22</a>	MPI_WIN_CALL_ERRHANDLER( win, errorcode ), <a href="#">21</a>	5
MPI_FILE_CALL_ERRHANDLER( fh, errorcode ), <a href="#">21</a>	MPI_WIN_CREATE_DYNAMIC, <a href="#">17</a>	6
MPI_FILE_CREATE_ERRHANDLER, <a href="#">9</a> , <a href="#">14</a>	MPI_WIN_CREATE_ERRHANDLER, <a href="#">9</a> , <a href="#">12</a>	7
MPI_FILE_CREATE_ERRHANDLER( file, errhandler ), <a href="#">13</a>	MPI_WIN_CREATE_ERRHANDLER( win, errhandler_fn, errhandler ), <a href="#">11</a>	9
MPI_FILE_GET_ERRHANDLER, <a href="#">9</a>	MPI_WIN_FREE, <a href="#">25</a>	10
MPI_FILE_GET_ERRHANDLER( file, errhandler ), <a href="#">14</a>	MPI_WIN_GET_ERRHANDLER, <a href="#">9</a>	11
MPI_FILE_OPEN, <a href="#">17</a>	MPI_WIN_GET_ERRHANDLER( win, errhandler ), <a href="#">12</a>	12
MPI_FILE_SET_ERRHANDLER, <a href="#">9</a>	MPI_WIN_SET_ERRHANDLER, <a href="#">9</a>	14
MPI_FILE_SET_ERRHANDLER( file, errhandler ), <a href="#">13</a>	MPI_WIN_SET_ERRHANDLER( win, errhandler ), <a href="#">12</a>	16
MPI_FILE_SET_VIEW, <a href="#">17</a>	MPI_WTICK, <a href="#">23</a>	17
MPI_FINALIZE, <a href="#">2</a> , <a href="#">3</a> , <a href="#">25</a> – <a href="#">30</a>	MPI_WTICK(), <a href="#">23</a>	18
MPI_FINALIZE(), <a href="#">25</a>	MPI_WTIME, <a href="#">4</a> , <a href="#">22</a> , <a href="#">23</a>	19
MPI_FINALIZED, <a href="#">24</a> , <a href="#">27</a> , <a href="#">29</a> , <a href="#">30</a>	MPI_WTIME(), <a href="#">22</a>	20
MPI_FINALIZED( flag ), <a href="#">29</a>	mpiexec, <a href="#">24</a> , <a href="#">28</a> , <a href="#">30</a> , <a href="#">30</a>	21
MPI_FREE_MEM, <a href="#">6</a> , <a href="#">7</a> , <a href="#">16</a>	mpirun, <a href="#">30</a>	22
MPI_FREE_MEM( base ), <a href="#">6</a>		23
MPI_GET_LIBRARY_VERSION, <a href="#">2</a> , <a href="#">24</a> , <a href="#">27</a>	typedef:MPI_Comm_errhandler_function(MPI_Comm *, int *, ...), <a href="#">10</a>	24
MPI_GET_LIBRARY_VERSION( version, resultlen ), <a href="#">2</a>	typedef:MPI_File_errhandler_function(MPI_File *, int *, ...), <a href="#">13</a>	25
MPI_GET_PROCESSOR_NAME, <a href="#">4</a> , <a href="#">5</a>	typedef:MPI_Win_errhandler_function(MPI_Win *, int *, ...), <a href="#">12</a>	26
MPI_GET_PROCESSOR_NAME( name, resultlen ), <a href="#">4</a>		27
MPI_GET_VERSION, <a href="#">2</a> , <a href="#">24</a> , <a href="#">27</a>		28
MPI_GET_VERSION( version, subversion ), <a href="#">1</a>		29
MPI_GROUP_FREE, <a href="#">9</a> , <a href="#">25</a>		30
MPI_INFO_DELETE, <a href="#">16</a>		31
MPI_INFO_FREE, <a href="#">25</a>		32
MPI_INIT, <a href="#">2</a> , <a href="#">3</a> , <a href="#">23</a> , <a href="#">27</a> – <a href="#">30</a>		33
MPI_INIT(), <a href="#">23</a>		34
MPI_INIT_THREAD, <a href="#">23</a> , <a href="#">29</a>		35
MPI_INITIALIZED, <a href="#">24</a> , <a href="#">27</a> – <a href="#">30</a>		36
MPI_INITIALIZED( flag ), <a href="#">27</a>		37
MPI_LOOKUP_NAME, <a href="#">16</a>		38
MPI_OP_FREE, <a href="#">25</a>		39
MPI_REGISTER_DATAREP, <a href="#">17</a>		40
MPI_REQUEST_FREE, <a href="#">25</a>		41
MPI_TEST, <a href="#">25</a>		42
MPI_TYPE_FREE, <a href="#">25</a>		43
		44
		45
		46
		47
		48